

SPIRou Quick Installation Guide

Version 0.0.26

For DRS SPIRou 0.1.006 (alpha pre-release)

This is a quick guide to installation, for a more full description please see the full documentation . This assumes you have the latest version of Anaconda for python 3 (or python 2) and are using a unix operating system with BASH.

1. Get the latest version of the DRS (for SPIRou version 0.1.006 (alpha pre-release)). from here: https://github.com/njcuk9999/spirou_py3
2. Download the test data from here: http://genesis.astro.umontreal.ca/neil/spirou_test_data_alpha0.1.003.zip (if required).
3. Extract the DRS (make a note of the path, hereinafter DRS_ROOT)
4. Add the following paths to your PATH and PYTHON PATH environmental variables (in for example .bashrc)

bash

```
export PATH="DRS_ROOT/bin/:<$PATH>"
export PYTHONPATH="DRS_ROOT:DRS_ROOT/bin/:<$PYTHONPATH>"
```

5. make sure your paths are set

bash

```
source ~/.bashrc
echo $PATH
```

6. Make recipes executable (found in the DRS_ROOT /bin folder) - to use from the command line.
7. Setup the DRS paths (edit the file: ‘../config /config.txt’):

| | | | |
|------------------|---------------------|---|--|
| TDATA | = /drs/data/ | / | Define the DATA directory |
| DRS_ROOT | = /drs/INTROOT/ | / | Define the installation directory |
| DRS_DATA_RAW | = /drs/data/raw | / | Define the folder with the raw data files in |
| DRS_DATA_REDUC | = /drs/data/reduced | / | Define the directory that the reduced data should be saved to/read from |
| DRS_CALIB_DB | = /drs/data/calibDB | / | Define the directory that the calibration files should be saved to/read from |
| DRS_DATA_MSG | = /drs/data/msg | / | Define the directory that the log messages are stored in |
| DRS_DATA_WORKING | = /drs/data/tmp/ | / | Define the working directory |

8. validate the DRS installation:

CMD input

```
>> cal_validate_spirou
```

or

CMD input

```
>> python cal_validate_spirou
```

The DRS is now installed and setup. To run see section ??.